

The Best-Run Businesses Run SAP

Technology

SAP NetWeaver Platform

7.0 EHP1

Basic Configuration for Connecting SAP SRM and SAP ERP

Use this wizard-based configuration task to configure the basic settings required for connecting SAP SRM and SAP ERP systems.

Procedure

Automatic Configuration

To carry out the wizard-based configuration task required for your SAP system, use the configuration wizard in the SAP NetWeaver Administrator.

1. Start the configuration wizard. For more information, see [Configuration Wizard](#).
2. Under **Show**, choose **All Configuration Tasks**.
3. Select **BS: SRM - ERP (Basic Configuration): Maintain** and choose **Start**.
4. If required, enter the necessary data and choose **Next**.

A list of the steps to be executed by the configuration wizard is displayed under **Details**. The steps are executed one after the other. The system makes the necessary settings and reports any configuration errors.

Mandatory Manual Configuration



Caution

Since some mandatory configuration steps are not yet supported by the configuration wizard, you will have to maintain the configuration steps manually. To perform these steps manually, follow the links below:

- [Adjusting Error Handler Settings \(SAP SRM\)](#)
- [Maintaining Site Attributes \(SAP SRM\)](#)
- [Stopping and Restarting Message Processing \(SAP SRM\)](#)

- [Maintaining Middleware Product Settings \(SAP SRM\)](#)
- [Maintaining Delta Load Settings \(SAP SRM\)](#)

Manual Configuration

If not all steps are executed successfully, you can perform the relevant step manually. Manual configuration is also necessary after an upgrade.

- [Creating Dialogue Users \(SAP ERP\)](#)
- [Creating RFC Destinations \(SAP ERP\)](#)
- [Defining Logical Systems \(SAP ERP\)](#)
- [Assigning Logical Systems to Clients \(SAP ERP\)](#)
- [Maintaining the TBLSYSDEST Table \(SAP ERP\)](#)
- [Registering Queues \(SAP ERP\)](#)
- [Maintaining Table CRMCONSUM \(SAP ERP\)](#)
- [Maintaining Table CRMRFPCPAR \(SAP ERP\)](#)
- [Maintaining Table CRMPAROLTP \(SAP ERP\)](#)
- [Maintaining Table CRMSUBTAB \(SAP ERP\)](#)
- [Scheduling Jobs \(SAP ERP\)](#)
- [Creating Dialog Users \(SAP SRM\)](#)
- [Defining Logical Systems \(SAP SRM\)](#)
- [Creating RFC Destinations \(SAP SRM\)](#)
- [Starting Application Monitors \(SAP SRM\)](#)
- [Maintaining the BBP_BACKEND_DEST Table \(SAP SRM\)](#)
- [Maintaining the TBLSYSDEST Table \(SAP SRM\)](#)
- [Registering and Starting Queues \(SAP SRM\)](#)
- [Activating Change Pointers Generally \(SAP SRM\)](#)
- [Scheduling Jobs \(SAP SRM\)](#)
- [Defining Middleware Parameters \(SAP SRM\)](#)
- [Scheduling Middleware Jobs \(SAP SRM\)](#)

Optional Configuration

The following configuration step is optional:

- [Maintaining Filters \(SAP SRM\)](#)

© COPYRIGHT BY SAP SE OR AN SAP AFFILIATE COMPANY. ALL RIGHTS RESERVED. –

PRINTED FROM SAP HELP PORTAL. (<http://help.sap.com>)
